

VPN User Guide: Contractors & External Users

Edinburgh Campus

Contents

- Windows 10 Client..... 2
 - Install the client 2
 - Set up the connection..... 2
 - Log in to the VPN 4
 - Disconnect 4
- Windows 10 App..... 5
 - Setting up the VPN connection..... 5
 - Log in to the VPN 5
 - Disconnect 5
- Apple Mac App 6
 - Setting up the VPN connection..... 6
 - Disconnect 7
- Browser – Alternative login 9
 - On your PC/laptop 9
 - Install the most recent version of JAVA..... 9
 - Using the VPN 10

Windows 10 Client

There is a 32 bit client and 64 bit client for Windows 10 installation.

Install the client

1. Download the client from <http://www.hw.ac.uk/is/it-essentials/virtual-private-network-vpn.htm>
2. Double click the **Sonicwall VPN Connection** shortcut on your desktop
3. Click **Yes** when prompted




Set up the connection

Once installed, you can set up the VPN.


1. Double click the **Sonicwall VPN icon** on your desktop 2.
Click **Next** at the Welcome... window




3. Enter **hwvpn.hw.ac.uk** in the host name field and click **Next**



4. Select **Contractors** from the dropdown, if support contractor – click **Next** or
Select **External User** from the dropdown, if External User – click **Next**




5. Click **Finish** to exit the wizard




Log in to the VPN


1. **Double click** the icon to open the VPN connection
2. Enter your HWU username and password
3. Click **Connect**



- The dialog box will show that you are connecting to the VPN



- Once connected, the VPN icon will display briefly in the Notification area indicating that it has connected



Disconnect

1. **Right click** on the VPN icon in the Notification area
2. Click **Disconnect**



Now open the Remote Desktop client or SSH shell to connect to the server

Windows 10 App

Download the **SonicWALL Mobile Connect App** from the Windows App store and follow the installation procedures.

Setting up the VPN connection

1. Click on **Start** and then **Settings**
2. Click on **Network & Internet**
3. Click on **VPN**
4. Click on **Add a VPN connection**
5. Select **SonicWALL Mobile Connect** from the VPN provider dropdown
Connection name: **heriot-watt**
Server name: **hwvpn.hw.ac.uk**
6. Click on **Save**

Log in to the VPN

1. Click on WiFi/Network icon in the Notification area
2. Click **heriot-watt**
3. Click on **heriot-watt** then click **Connect**
4. Click **Next**
5. Enter your HWU UserID and password
6. Click **OK**
7. **Close** window

Disconnect

1. Click the WiFi/Network icon in the Notification area
2. Select **heriot-watt**
3. Click on **heriot-watt** and then click **Disconnect**



Apple Mac App

Download the **SonicWALL Mobile Connect App** from the Apple store and follow the installation procedures.

Setting up the VPN connection


Open the App 



2. Highlight **Add Connection**
3. Hit **[Return]**




- 1.
4. Enter the **Name** and **Server** details in the dialog box
 - Name: **heriot-watt**
 - Server: **hwvpn.hw.ac.uk**
5. Click **Next**




6. Click **Connect**



7. Select **Contractors** from dropdown, if support contractor- Click **Next** or Select **External User** from dropdown, if external user – Click **Next**



8. Enter your **Username** and **Password** 9. Click **Login**




- You are now connected to the HW Edinburgh VPN



Disconnect

- Remember to disconnect from the VPN via the SonicWALL App when finished



Browser – Alternative login

The browser offers an alternative way to log in if there is any reason you cannot use the APP – ***you should not use both together.***

The following instructions tell you how to setup and install the software required to connect to the Heriot-Watt Edinburgh VPN via your browser.

On your PC/laptop

Install the most recent version of JAVA

You can download **JAVA** here <http://www.java.com/en/download>


Edit your JAVA settings

1. Go to the **Java Control Panel** (open **System preferences** – then open **Java**)
2. Select the **Security** tab
3. Click **Edit Site List**
4. Click **ADD**
5. Type **https://hwvpn.hw.ac.uk** in the new row
6. Click **OK**


Using the VPN

Log in to VPN

1. Open a browser (Firefox preferred) and go to <https://hwvpn.hw.ac.uk>
2. Select **Contractors** from dropdown, if Support Contractor - Click **Next** or Select **External User** from dropdown, if External User – Click **Next**




3. Enter your **HW Username** and **Password** 4. Click **Log in**




- If prompted click on **Allow** to run JAVA

5. Click **Install** at the Secure Endpoint Manager page





- The Portal page access should be **Access: Full Network Access**



You are now connected to the VPN.

If this shows **Access: Web** please re-check your settings and login.

Log out

- Click **Logout** to close VPN connection